

# LOVE2BREW

## WANDERLUST – ENGLISH IPA (PARTIAL MASH)



Tired of the same old IPAs? Interested in a beer experience that takes you to a different place? Our Wanderlust English IPA combines the traditional IPA brewing style with English malts and hops for a totally unique IPA experience. Wanderlust has a strong malt backbone with big notes of bread, toast, and some slight caramel flavors. All English hops provide a bold range of flavors such as earthy, hop spice, dank notes of grass, with hints of floral aromatics that round out the beer very well. True to style this English IPA has a moderate bitterness and a flavor profile that strays from the highly bitter and citrus road that is so common in many modern India Pale Ales. Feed your curiosity, try a different kind of IPA today and enjoy the rewards of your own wanderlust.

### KIT STATISTICS

- 2 Weeks Primary Fermentation
- 5 Days Secondary Fermentation
- 2 Weeks Bottle Conditioning
- Original Gravity: 1.065
- 6.2% ABV (Estimated)
- IBUs: 57.5
- SRM: 10.6 (Dark Gold)
- 60 Minute Boil

### HOME BREW KIT CONTENTS

#### Malts & Specialty Grains

- 5 lbs. Light Malt Extract
- 2.5 lbs. Maris Otter
- 8 oz. Carastan
- 8 oz. Biscuit Malt
- 8 oz. Caramel 40L

#### Hops

- 2 oz. UK Challenger (Bittering)
- 2 oz. UK Kent Goldings (Aroma)
- 1 oz. Fuggles (Aroma)
- 1 oz. UK Target (Aroma)
- 1 oz. UK Kent Goldings (Dry Hop)

#### Yeast Choices

- Safale US-05
- Nottingham Ale Yeast
- London Ale Yeast (WLP013)

#### Other

- 5 oz. Priming Sugar

### EQUIPMENT:

- 2x Brew Kettles (3.5+ gallon capacity)
- Thermometer & Hydrometer
- 2x Fermentation Vessels
- Stirring Spoon
- Airlock
- Blow off tubing
- Bottles
- Racking Equipment
- Sanitizer
- Large Nylon Straining Bag
- Wire/Mesh Strainer

### GETTING STARTED:

- If you haven't already done so read the "Basic of Brewing" guide included in your equipment kit.

- Read over the entire contents of this recipe before you brew. This will help avoid any errors. You are adding the malt extract in two separate additions for this batch.

- Upon receiving your kit refrigerate your yeast. One day before your brew day remove your yeast from your refrigerator and allow it reach room temperature. (~70°F)

- Clean and Sanitize all equipment thoroughly; poor sanitization could ruin an otherwise perfect batch.

- Crush grains: Many of our grains come pre-crushed; however it never hurts to examine your specialty grains first. If un-crushed simply using a rolling pin to crush grains.

- You'll need approximately 4 hours to complete this brew. Schedule accordingly.

- Homebrew (To enjoy in moderation while brewing)\*

\*Optional

## BREW YOUR BEER

1. Heat 1 gallon (4 qt.) of water to 157°F
2. Turn the burner off and line your brew kettle with the mesh/nylon bag.
3. Slowly add your all crushed grains to the bag lined kettle. Your grain/water mixture is now referred to as the "mash".
4. Slowly stir your mash until have an even mix of grain and water. Your objective is to achieve an even temperature of **152°F**.
5. Cover your brew kettle and maintain the mash temperature for 60 minutes.  
\* An easy way to maintain temp. is to set your oven to warm and stick your kettle in the oven. If this is not an option you may wrap your kettle in old blankets or towels to help insulate.
6. Once Kettle is resting collect 2.5 Gal. (10 qts.) water and heat to 168°F. This will be used to **sparge**. Maintain temperature.
7. After 60 minute Sach rest is complete return lift the bag out of kettle and place in strainer over kettle; let the wort drain.
8. Slowly pour sparge water evenly over the grain bag. This is the sparging process. Pour until sparge water is complete. Once dripping has stopped remove spent grains and discard/compost/save/etc.
9. 60 Minutes: Add 3 lbs. Light Malt Extract. Stir.
10. Once the foaming subsides begin your 60 minute boil process. Timing is referred to by minutes left in the boil.
11. 60 Minutes: Add 2 oz. of UK Challenger for Bitterness.
12. 30 Minutes: Add 2 lbs. Light Malt Extract. Stir.
13. 10 Minutes: Add 1 oz. of UK Kent Goldings for Aroma.
14. 5 Minutes: Add 1 oz. of Fuggles for Aroma.
15. 5 Minutes: Add 1 oz. of UK Target for Aroma.
16. 0 Minutes: Add 1 oz. of UK Kent Goldings for Aroma.
17. After your wort is done boiling it is very important you cool it as quickly as possible.. Create an ice bath (ice and water) in your sink and set the brew kettle in it. You need to cool your wort down to 90°F or lower.

## COOLING / TRANSFERRING

1. By now all of your equipment should be already sanitized; if not sanitize your screw cap, fermenting vessel, airlock, siphon, and tubing.
2. Fill your primary fermentor with 1 gallon of cold water.
3. Pour your cooled wort into the primary fermentor. Avoid dumping the sludge on the bottom into your fermentor.
4. Add cold water as needed to bring wort up to 5 gallons of liquid ensuring that it is below 70°F.
5. Seal the fermentor and aerate the wort by rocking the fermenting vessel back and forth a bit.
6. Measure Specific Gravity of the wort with your hydrometer and record.
7. Add yeast to fermenting vessel. It is important that the wort temperature not be above 70°F when adding the yeast.
8. Seal the fermentor. Add an airlock or blow-off tube.

## FERMENTING

1. Move fermenting vessel to a room temperature dark spot (approximately 68°F).
2. You will observe active fermentation within about 48 hours. You want to maintain the temperature of approximately 68°F.
3. After about 1-2 weeks your active fermentation will stop. At this point if you have a blow off tube attached you may remove it and add an airlock to the vessel.
4. After 2 weeks transfer your beer to the secondary fermentor. Transferring is as simple as siphoning from the primary to the secondary.
5. After you have transferred your beer to the secondary fermentor add 1 oz. of UK Kent Goldings to dry hop.
6. After 5 days of secondary fermentation you are ready to bottle or keg your beer.

## BOTTLING / CARBONATING

1. Sanitize your bottles, bottle caps, bottling bucket, siphon tubing, siphon, and bottling wand.
2. Add priming sugar to 16 oz. of water and bring the mixture to a boil using your stove. Let cool and add to your bottling bucket.
3. Gently siphon beer into bottling bucket; avoid splashing.
4. Fill and cap bottles.
5. Condition bottles for 2 weeks at room temperature.
6. After 2 weeks you may store the bottles in a cool/cold location if carbonated.

## ENJOY!

1. Pour your homebrew into a clean glass. For aesthetic reasons many people avoid pouring the yeast in but it won't hurt you!
2. Smell the beer, a few short sniffs. Taste. Allow beer to cover the tongue, swallow. Smile. Life is good.

If you have any questions while brewing your beer call us at 1.888.654.5511 or email [support@love2brew.com](mailto:support@love2brew.com). We're open 7 days a week to help you brew the best beer possible!

Be sure to visit [www.love2brew.com](http://www.love2brew.com) for new recipes and ingredients! In addition we feature new articles daily about brewing and our [love2learn](#) section which houses one of the largest homebrewing article collections in the world!